



Change Log FSI Pages mobile

Version 1.0.4

- **FIXED:** cross-domain issues (CORS)

Version 1.0.5

- **ADDED:** full text search
- **ADDED:** navigation buttons in thumb view enabled/disabled depending on position
- **ADDED:** improved debug window output (XML parse errors, HTTP errors)
- **ADDED:** splash image on start-up (images/startup.png)
- **ADDED:** optional parameter `MobileAboutWindow=false` to disable the about box option (requires a valid license key)
- **ADDED:** support for `ConfigCaching` parameter
- **FIXED:** page number did not re-appear when page number input loses focus
- **FIXED:** occasional script error "pagesOffsets undefined" on load
- **FIXED:** mime type issues with *.fsi files
- **FIXED:** Chapters plug-in item height

Version 1.0.6

- **FIXED:** improved initialization stability
- **FIXED:** eliminated a gap occurring on Android 2.2 and above devices

Version 1.0.7

- **FIXED:** Inconsistency of the XMLBase parameter with the desktop version
- **FIXED:** Scrolling of pages stopped when swiping vertically while the pages are already scrolling
- **FIXED:** Clicking hyperlinks did not work on some Android devices
- **FIXED:** Improvements to the pinch zoom gesture
- **FIXED:** FSI Pages parameter "XMLBase" with an empty value does not request XML files anymore. Use at least the value "/" to load XML files.

Version 1.0.8

- **FIXED:** Page offset after zooming and using the library plug-in to change the publication
- **FIXED:** Additional click required after closing the help dialog

Version 1.0.9

- **FIXED:** Zoomed image size after rotating the device multiple times
- **FIXED:** Position of hyperlinks when using "EmptyImages" parameter
- **FIXED:** Zoom position on Android devices
- **FIXED:** Reload issue on iPhone4 in popup windows
- **FIXED:** Interface size on iPhone4 Retina screen
- **FIXED:** Hyperlink dialog height on small screens
- **FIXED:** javascript: hyperlinks with target "_self" have been executed in an incorrect scope
- **FIXED:** Default link target is now "_self" instead of "_blank", like in FSI Pages (desktop)

Version 1.1.0

- **Added:** "MobileQuitButton" option adds a "Close Window" option to the menu. The default is "true" for FSI Pages mobile in popup windows.

Version 1.1.1

- **FIXED:** Page number input was empty on iOS 5.x versions
- **FIXED:** Tool tips in <text> nodes containing unencoded HTML tags have been ignored
- **FIXED:** error when searching in catalogs containing blank pages
- **FIXED:** page numbering was different to FSI Pages desktop when using "frontcover=false"

Version 1.1.2

- **FIXED:** Left pages failed to display zoomed images with parameter PageBorderColor set to "false"
- **FIXED:** Orientation change on iPhone 4 sometimes lead to page sizes not filling up the available space

Version 1.1.3

- **FIXED:** plug-in pageslibrary: missing support for parameter "showLabels"

Version 1.1.4

- **FIXED:** plug-in chapters: missing support for FSI Pages parameter "firstPageNumber"
- **FIXED:** plug-in chapters: missing support for parameter "useFirstPageNumber"
- **FIXED:** plug-in chapters: missing support for parameter "usePageNameAliases"
- **FIXED:** plug-in chapters: missing support for parameter "pageNumbers"
- **FIXED:** plug-in chapters: missing support for parameter "pageNumberPrefix" and "pageNumberSuffix"

Version 1.1.5

- **FIXED:** #zoomArea links not working
- **FIXED:** #zoomArea and #zoom now zoom to the hyperlink shape's center
- **ADDED:** #showImage link option

Version 1.1.6

- **ADDED:** New parameter "headers". Default is "cors" to prevent cross domain access issues when using HTML documents on domains other than the FSI Server domain. Supported by FSI Server from version 3

Version 1.1.7

- **FIXED:** changing orientation with content of less than 2 double-pages lead to inaccessible pages in portrait view

Version 1.1.8

- **FIXED:** lock if localStorage is unavailable (e.g. in Chrome for iOS in some situations)

All brands and product names are trademarks or registered trademarks of the respective owners.
FSI Viewer is a registered trademark of NeptuneLabs GmbH, Germany.
© 2003-2013 NeptuneLabs. All rights reserved.